



Onsatmail Grib files

How to setup a request for grib files:

1. Open the Onsatmail application then select "utilities" from the top of the main page and then select web fetch



2. Select new grib at the top left of the screen



3. In the saildocs screen, select the command drop down menu and choose subscribe

SailDocs Grib Request

Grid Coverage: 10 x 20 Deg. Location: x

Set Grib Cancel Save

Description: Command: Subscribe Latitude: 60N Longitude: 07N, 188W, 24W Grid: 2x2 Send Email

Times: 6 12 18 24 36 48 72 96

Prms: Press Wind Wave Sea Temp Air Temp HGT (500mb)

Time: Subscribe for: 14 Days (0-30)

Email Cmd Line: sub gfs:60N,07N,188W,24W|2,2|24,48,72|PRESS,WIND days=14

4. Enter the desired lat and long of the grib file you want to receive
5. Select how often you would like to receive a report for this area and also the parameters of the report, (pressure, wind air temp etc...)

SailDocs Grib Request

Grid Coverage: 10 x 20 Deg. Location: x

Set Grib Cancel Save

Description: Command: Subscribe Latitude: 60N Longitude: 07N, 188W, 24W Grid: 2x2 Send Email

Times: 6 12 18 24 36 48 72 96

Prms: Press Wind Wave Sea Temp Air Temp HGT (500mb)

Time: 12:00 Subscribe for: 14 Days (0-30)

Email Cmd Line: sub gfs:60N,07N,188W,24W|2,2|24,48,72|PRESS,WIND time=12:00 days=14


6. Select the time of day that you would like to receive the grib and also how long you would like the grib files to be sent to your inbox
7. Select send email and the request will be sent through when you next make a normal onsatmail connection. After about a minute you will receive confirmation from saildocs of your grib request.
8. the requested grib files will now be sent to your inbox as per your requested time and for your requested subscription length.

NOTE: You have to make a connection for the files to be downloaded into your inbox


Downloading the grib viewer:

Onsatmail has an application to view grib files, this is a 1Mb download and will be sent to your inbox. It is recommended that this is downloaded through a VPN connection and not an Iridium/Thuraya.


1. Open the Onsatmail application and select setup, at the top right of the screen



2. On the setup screen select the MISC tab on the far right



3. Select download grib viewer, there will be a message saying that the size of the file is a meg and would you like to still download the file. Select Download



When you next make a connection the Grib viewer will be downloaded into your inbox. This will have to be saved onto your computer and installed through the inbuilt install wizard.

NOTE: If this is the first time you are viewing a grib file from onsatmail, you will have to right click on the selected grib file and select "open with" and then select grib viewer