



OnSatMail Quick Start Guide – MAC

Below is a quick start guide to installing and setting up OnSatMail on a MAC. Please make sure that your equipment is connected to your Mac before the setting up of your OnSatMail. Your equipment will need good signal and be registered on the network.

Installing:

- Browse to www.onsatmail.com
- From the left hand side, select the MAC version of OnSatMail
- Open the **UUPlus6_Mac.zip** to make the **UUPlus6_Mac folder**.
- In the folder double click on **setup6.app.tar**. This will unpack the TAR file
- Double click on the **setup6.app** to begin the installation.
- The installer may not appear on the screen and instead be found bouncing in the dock. Click on the bouncing icon to see the install window
- Install the UUPlus Personal software.
- Please enter your information as requested. NOTE: your account number will be your voice number
- Click **[Yes]** to enable the **POP/SMTP Servers**
- Your OnSatMail will now be installed

Setting up your OnSatMail:

- Open your OnSatMail application to the main page (A large white screen should appear)
- Click on the **setup tab** in the top right hand corner of the screen
- Click the **calling tab** in the new screen
- Select “**add new location**”



- From the drop down menu select the type of modem you are using (Iridium, Inmarsat, Globalstar, Thuraya)
- Click **find modem** to search all available ports for the connection. You should see it appear in the bottom box
- Click **install**
- Return to the main OnSatMail page
- Click the **call tab** in the top left hand side of the screen
- A **dial up** box should appear and your equipment should show there is a data call in progress.
- Any messages waiting to be sent should then be sent and at the same time you should receive any messages waiting in your Inbox
- Whenever you want to reconnect from this point on just click the call tab.

Setting up for Apple Mail:

- Start the wizard if it doesn't start automatically for you.
- Fill out your UUPlus account info and click [Continue].
- Enter a Description for the incoming mail server.
- Incoming mail server: 127.0.0.1 5 Click [Continue].
- Apple Mail will give an error that the POP server is not responding. Ignore it and click [Continue].
- For Incoming Mail Security don't check anything. Just click [Continue].
- Enter a Description for the Outgoing Server.
- Outgoing Mail Server: 127.0.0.1 Click [Continue].
- Apple Mail will once again produce an error. Ignore it and click [Continue].
- No Outgoing Mail Security. Click [Continue].



- Apple Mail will display the summary of the account. Click [Create].
- From the main application window go to [Mail --> Preferences].
- Select the [Accounts] section.
- Select the UUPlus account and under [Account Information] pull down the Outgoing Mail Server box and select "Edit Server List."
- Select the UUPlus server and change to the [Advanced] tab.
- Change the Server port from 465 or 25 to 1025 and click [OK].
- Select the UUPlus account and change to the Advanced tab under the main Accounts section.
- Change the POP port from 110 to 1110.
- Close the Preferences window and [Save] your changes.

For Help and Support with this please contact AST:

Phone: +44 (0)1493 441 485

Email: customer.service@ast-uk.com

Skype: AST Customer Services

